


# Raster Data Analysis







## **ArcGIS Spatial Analyst**

- Mainly for raster data analysis
- Arctoolbox: Spatial Analyst Tools
- Spatial Analyst Toolbar
  - Raster Calculator







#### Raster Calculator Functions Help <u>I</u>opics <u>B</u>ack Glossary Commands An alphabetical list of GRID functions Arcinfo ABCDEFGHIJKLMNOPQRSTUVWXYZ Related Topics Workstation / calculates the curvature of a surface at each cell center D Arcdoc calculates the groundwater volume balance residual for steady state flow in an aquifer and the seepage velocity for each cell using Darcy's Law. converts a USGS DEM to a grid. DARCYFLOW DEMGRID DTEDGRID converts a US NIMA DTED file into a grid. edits a signature file by merging, renumbering and deleting class signatures and creates a new signature file. EDITSIG > 200 functions creates a new signature tile, eventuates, or a cell-by-cell basis, the number of times in an argument list that the input grid values are equal to the value specified by the first argument, calculates for each cell the zone of the closest source cell (in Euclidean distance), calculates the direction in degrees that each cell center is from the cell center of the closest source. The output values are based on compass directions, with 0.0 being reserved for the source cells. EQUALTO EUCALLOCATION EUCDIRECTION calculates for each cell the Euclidean distance to the closest source. EUCDISTANCE EXP EXP10 calculates the basee exponential of the input. calculates the base10 exponential of the input. EXP2 calculates the base2 exponential of the input. expands the selected zones by a specified number of cells. flips a grid along a horizontal axis. converts integer values to floating-point values. converts a file of binary floating point numbers to a grid. returns the greatest integer value that is smaller than or equal to the input values. creates a grid of accumulated flow to each cell, by accumulating the weight for all cells that flow into each downslope cell. FLIP FLOAT FLOATGRID created a grid of flow direction from each cell to its





### Working with Nodata in RC


- ISNULL: convert Nodata to a value
- SETNULL: set cell value to Nodata
- CON: conditional function
- Examples
  - Replace Nodata with 0 in a DEM
    Outgrid = con(isnull([dem]), 0, [dem])
  - Set slope > 15 to Nodata on the DEM
    Lowrisk = setnull([slope] > 15, [dem])




















# 







# Implementing Ordered Weighted Average in ArcGIS

Raster Calculator

```
r1 = rank(1, [factor1], [factor2], [factor3])
r2 = rank(2, [factor1], [factor2], [factor3])
r3 = rank(3, [factor1], [factor2], [factor3])
owavg = [r1] * 0.5 + [r2] * 0.3 + [r3] * 0.2
```